USB Driver Installation


- (1) Connect one end of a USB cord to your PC.
- (2) Set the Function switch on the instrument to SET UP range, and connect the other end of USB cable to the instrument.




(3) When your PC and the instrument are connected properly, the following figure appears. Select "Locate and install driver software (recommended)".

Found New Hardware
Windows needs to install driver software for your KEW POWER METER 6300
Locate and install driver software (recommended) Windows will guide you through the process of installing driver software for your device.
Ask me again later Windows will ask again the next time you plug in your device or log on.
Don't show this message again for this device Your device will not function until you install driver software.
Cancel

(4) Select "Don't search online".



(5) Select "I don't have the disc. Show me other options".



(6) Select "Browse my computer for driver software(advanced)".

e 1	Found New Hardware - KEW POWER METER 6300	
Wi	ndows couldn't find driver software for your device	
4	<u>Check for a solution</u> Windows will check to see if there are steps you can take to get your device working.	
	Browse my computer for driver software (advanced) Locate and install driver software manually.	
		Cancel

(7) Check the boxes for "Include subfolders", and then click "Browse".

G I Found New Hardware - KEW POWER METER 6300	
Browse for driver software on your computer	
Search for driver software in this location:	
D:\C3300\ENG	Browse
Include subfolders	
	Next Cancel

(8) Select a folder to download the file.

Browse For Folder Select the folder that contains drivers for your hardwa	are.
🧮 Desktop	
kaihatsu_language	
Public	
D State Computer	
Network	
POWER_METER	
🎍 amd64	
i386	
To view subfolders, click the symbol next to a folder.	
OK Cano	el


(9) It's confirmed that a chosen folder is indicated, and click "Next".

G	Found New Hardware - KEW POWER METER 6300	×
	Browse for driver software on your computer	
	Search for driver software in this location:	
	✓ Include subfolders	
	<u>N</u> ext Can	cel

(10) In case that following window appears on Windows Vista, click "Install this driver software anyway". (It is an operation check, and no problem happens if install is continued.)

😵 Wir	ndows Security
\otimes	Windows can't verify the publisher of this driver software
	Don't install this driver software You should check your manufacturer's website for updated driver software for your device.
	Install this driver software anyway Only install driver software obtained from your manufacturer's website or disc. Unsigned software from other sources may harm your computer or steal information.
	See <u>d</u> etails


(11) Install is completed when the wizard finishes. Click "Close".



(12) When installation above-mentioned ends, the following figure appears. Select "Don't search online". After that, step (5) to (11) will be repeated twice.

G	<u>n</u>	Found New Hardware - USB Serial Port
	Allo	w Windows to search online for driver software for your USB Serial Port?
	•	Yes, always search online (recommended) Windows will automatically search for the latest drivers and applications for your hardware and download them to your computer.
	•	Yes, search online this time only Windows will search for the latest drivers and applications for this device and download them to your computer.
	•	Don't search online Your device may not function properly until you get the latest software.
	Pleas	e read Microsoft's privacy statement
		Cancel


(13) When 2 being installed as shown in the lower figure, a driver was normally installed.



USB Driver Un-installation

When install of the USB driver is interrupted and reinstall cannot be done, follow the procedure below and delete the existing driver, and then install it again.

- (1) Connect a PC and the instrument with a USB cord.
- (2) Click the "Control Panel" in the Start menu.
- (3) Click "Device Manager" in the Control panel.
- (4) Right click on "KEW POWER METER 6300" in the Other devices.
- (5) Click "Uninstall" to uninstall the USB driver.



- (6) Remove the USB cord connecting your PC and the instrument once, and connect them again.
- (7) When "Found New Hardware Wizard" window appears, follow the procedures described at "**USB Driver Installation**" and install the driver.