
## **USB Driver Installation**

- (1) Connect one end of a USB cord to your PC.
- (2) Connect the other end of USB cord to the Communication Adapter.
- (3) When your PC and the instrument are connected properly, the following figure is indicated. Select "Locate and install driver software (recommended)".



(4) Select "Don't search online".

Found New Hardware - MODEL 8241	
Allow Windows to search online for driver software for your MODEL 8241?	
Yes, <u>a</u> lways search online (recommended) Windows will automatically search for the latest drivers and applications for your hardware and download them to your computer.	
Yes, search online this time only Windows will search for the latest drivers and applications for this device and download them to your computer.	
Don't search online Your device may not function properly until you get the latest software.	
Please read Microsoft's privacy statement	
Cancel	

(5) Select "I don't have the disc. Show me other options".

G	Found New Hardware - MODEL 8241
	Insert the disc that came with your MODEL 8241 If you have the disc that came with your device, insert it now. Windows will automatically search the disc for driver software.
	I don't have the disc. Show me other options.
	<u>N</u> ext Cancel

(6) Select "Browse my computer for driver software(advanced)".

G	۵	Found New Hardware - MODEL 8241	×
	Win	dows couldn't find driver software for your device	
	•	<u>C</u> heck for a solution Windows will check to see if there are steps you can take to get your device working.	
	•	B <u>r</u> owse my computer for driver software (advanced) Locate and install driver software manually.	
			Cancel

(7) Check the boxes for "Include subfolders", and then click "Browse".

	Found New Hardware - MODEL 8241	×
	Browse for driver software on your computer	
	Search for driver software in this location:	
	D:\C3300\ENG    Browse	
-	Include subfolders	
	Next	Cancel

(8) Select a folder to download the file.

	Select the folder that contains drivers for your hardware.
[	Nesktop
	kaihatsu_language
	Public
	Computer
	🛛 👰 Network
	A 🚺 DRIVER
	🍌 amd64
	🎍 i386
L	
1	To view subfolders, click the symbol next to a folder.
	OK Cancel

(9) It's confirmed that a chosen folder is indicated, and click "Next".

Found New Hardware - MODEL 8241	
Browse for driver software on your computer	
Search for driver software in this location:	Province
Include subfolders	B <u>r</u> owse
	<u>N</u> ext Cancel

(10) In case that following window appears on Windows Vista, click "Install this driver software anyway". (It is an operation check, and no problem happens if install is continued.)

Win	ndows	Security
$\bigotimes$	Win	dows can't verify the publisher of this driver software
	•	<u>D</u> on't install this driver software You should check your manufacturer's website for updated driver software for your device.
	•	Install this driver software anyway Only install driver software obtained from your manufacturer's website or disc. Unsigned software from other sources may harm your computer or steal information.
<u>ی</u>	See <u>d</u> et	ails

(11) Install is completed when the wizard finishes. Click "Close".


Found New Hardware - MODEL 8241	×
The software for this device has been successfully installed	
Windows has finished installing the driver software for this device:	
MODEL 8241	
	Close

(12) When installation above-mentioned ends, the following figure appears. Select "Don't search online". After that, step (5) to (11) will be repeated twice.

(

Generation International Second Port	x
Allow Windows to search online for driver software for your USB Serial Port?	
Yes, always search online (recommended) Windows will automatically search for the latest drivers and applications for your hardware and download them to your computer.	
Yes, search online this time only Windows will search for the latest drivers and applications for this device and download them to your computer.	
Don't search online Your device may not function properly until you get the latest software.	
Please read Microsoft's privacy statement	
Cancel	


(13) When 2 being installed as shown in the lower figure, a driver was normally installed.



## **USB Driver Un-installation**

When install of the USB driver is interrupted and reinstall cannot be done, follow the procedure below and delete the existing driver, and then install it again.

- (1) Connect a PC and the instrument with a USB cord.
- (2) Click the "Control Panel" in the Start menu.
- (3) Click "Device Manager" in the Control panel.
- (4) Right click on "MODEL 8241" in the Other devices.
- (5) Click "Uninstall" to uninstall the USB driver.



- (6) Remove the USB cord connecting your PC and the instrument once, and connect them again.
- (7) When "Found New Hardware Wizard" window appears, follow the procedures described at "**USB Driver Installation**" and install the driver.